

SAP ABAP table VKKACONDIT {Gen. Condition Transfer: Condition Key}

VKKACONDIT-KNUMA AG = KONA-KNUMA

VKKACONDIT
MANDT [CLNT (3)]
KVEWE [CHAR (1)]
KOTABNR [NUMC (3)]
KAPPL [CHAR (2)]
KSCHL [CHAR (4)]
KZUST [CHAR (3)]
KNUMA_PI [CHAR (10)]
KNUMA_AG [CHAR (10)]
KNUMA_SQ [CHAR (10)]
KNUMA_SD [CHAR (10)]
KNUMA_BO [CHAR (10)]

KONA
MANDT [CLNT (3)]
KNUMA [CHAR (10)]

T000
MANDT [CLNT (3)]

T681
KVEWE [CHAR (1)]
KOTABNR [NUMC (3)]

T681A
KAPPL [CHAR (2)]

T681V
KVEWE [CHAR (1)]

T685
MANDT [CLNT (3)]
KVEWE [CHAR (1)]
KAPPL [CHAR (2)]
KSCHL [CHAR (4)]

T686C
MANDT [CLNT (3)]
KZUST [CHAR (3)]

{0,1}

0..N

{0,1}

{0,1}

{0,1}

1

1

1

1

{0,1}

0..N

VKKACONDIT-KNUMA_BO = KONA-KNUMA

0..N

VKKACONDIT-KNUMA_PI = KONA-KNUMA

0..N

0..N

VKKACONDIT-KNUMA_SD = KONA-KNUMA

0..N

0..N

VKKACONDIT-KNUMA_SQ = KONA-KNUMA

VKKACONDIT-MANDT = T000-MANDT

0..N

VKKACONDIT-KOTABNR = T681-KOTABNR

VKKACONDIT-KAPPL = T681A-KAPPL

1

VKKACONDIT-KVEWE = T681V-KVEWE

1

VKKACONDIT-KSCHL = T685-KSCHL

1

VKKACONDIT-KZUST = T686C-KZUST

0..N

0..N